

Description of making Suse 8.2 to X-terminal server.

/home/ottar/backup/xterminal.txt

/etc/sysconfig/displaymanager

Set
KDM_SHUTDOWN="local"

/etc/opt/kde3/share/config/kdm/kdmrc

Section [Xdmcp]
set following values:
- Enable=true
- Port=177

/usr/lib/X11/xdm/xdm-config

Comment out ! DisplayManager.requestPort: 0

XDMCP and Security (or how use Xterminals with XDM)

=====

By default XDMCP is disabled, this means that a remote Xterminal can not contact this XDM. In order to use XDMCP the resource line with `DisplayManager.requestPort` in the file `xdm-config` should be commented out. This enables the XDMCP port with the default port number 177 (see `/etc/services`).

Please configure access rules within the file `Xaccess` for your Xterminals. These rules are host based and/or domain based to allow or deny contact on the XDMCP port. For some example see the manual page of `xdm(1)`, section 'XDMCP ACCESS CONTROL' and the section 'CHOOSE'.

To force a rescan of `Xaccess` and `xdm-config` within a running XDM the signal `SIGHUP` can be used:

```
kill -HUP `cat /var/run/xdm.pid`
```

The change of `DisplayManager.requestPort` requires a restart of XDM.

--
Have a lot of fun...

Your SuSE Team

XDM configuration for SuSE Linux
=====

xdm-config: The configuration of xdm.
`authName` should be in general MIT-MAGIC-COOKIE-1 --
for XDM-AUTHENTICATION-1 which is default for xterminals
see man page of xdm and the manual coming with the
specific xterminal.

NOTE: In order to use XDMCP this feature the resource
DisplayManager.requestPort in xdm-config should
be commented out to enable XDMCP.

Xaccess: The XDMCP access control file, see note above.

Xsetup: Handle all local and remote X Window System consoles.
For BackGround pictures go here and read.

RunChooser: Handle the remote chooser call. For BackGround pictures
go here and read.

Xstartup: Do log on of the (remote) user. Write utmp/wtmp/lastlog
entries for the session. If system console is used
give to the current virtual console to the user

GiveDevices: Give the current virtual and logging consoles over
to the user. Any other device which should be given
the user of display :0 should be added herein.
Called by Xstartup.

Xreset: Do log off of the (remote) user. Reset utmp/wtmp/lastlog
entries for the session. If system console was used
Take back the current virtual console.

TakeDevices: Take the current virtual and and logging console back.
Any other device which was given away should be taken
back herein. Called by Xreset.

Xresources: Disable the possibility to abort the xdm display
for any user. They can use <Ctrl>-<Alt>-<BackSpace>

Xsession: Setup the xsession and start the xsession script of
the user.

sys.xsession: Fallback for Xsession script

Xservers: The X server(s) for e.g. local console.

Xservers.fs: An alternate Xservers file for system without display
being server for X terminals. It is a replacment for
Xservers in xdm-config.

Xwilling: Generate the status line at a XDMCP broadcast query
for a remote chooser menu.

--
Have a lot of fun...

Your SuSE Team